HOW TO UNDERSTAND A TA1 REPORT

1

↓

a

↓

ISA*00*   *00*   *ZZ*382069753   *ZZ*C0XXX   *150629*1657*{*00501*000005161*0*P*>~

2   **a**   **b**   **c d e**

↓   ↓   ↓   ↓ ↓ ↓

TA1*000005161*150608*1137*R*025~

3

↓

IEA*1*000005161~

1. The ISA (Interchange Control Header) segment starts and identifies an interchange of zero or more functional groups and interchange-related control segments.

    1a. Unique Submitter Id issued from BCBS

2. The TA1 segment acknowledges the receipt and or syntactical correctness of an X12 interchange header and trailer (ISA/IEA) pair. The segment consists of five separate elements:

    2a. Interchange Control Number of submitted file.

    2b. Interchange Date (formatted as YYMMDD)

    2c. Interchange Time (Military time formatted as HHMM)

    2d. Interchange Acknowledgement Code:

Code Description
A Interchange accepted with no errors.
R Interchange rejected because of errors. Sender must resubmit file.
E Interchange accepted, but errors are noted. Sender must **not** resubmit file.

2e. Interchange Note Code (see below, Table of TA1 Errors)

3. The IEA (Interchange Control Trailer) segment defines the end of an interchange of zero or more functional groups and interchange-related control segments.

Table of TA1 ERRORS:

000 No error
001 The Interchange Control Number in the header and trailer do not match. Use the value from the header in the acknowledgment.
002 This Standard as noted in the Control Standards Identifier is not supported.
003 This Version of the controls is not supported
004 The Segment Terminator is invalid
005 Invalid Interchange ID Qualifier for sender
006 Invalid Interchange Sender ID
007 Invalid Interchange ID Qualifier for receiver
008 Invalid Interchange Receiver ID
009 Unknown Interchange Receiver ID
010 Invalid Authorization Information Qualifier value
011 Invalid Authorization Information value
012 Invalid Security Information Qualifier value
013 Invalid Security Information value
014 Invalid Interchange Date value
015 Invalid Interchange Time value
016 Invalid Interchange Standards Identifier value
017 Invalid Interchange Version ID value
018 Invalid Interchange Control Number
019 Invalid Acknowledgment Requested value
020 Invalid Test Indicator value
021 Invalid Number of Included Group value
022 Invalid control structure
023 Improper (Premature) end-of-file (Transmission)
024 Invalid Interchange Content (e.g., invalid GS Segment)
025 Duplicate Interchange Control Number
026 Invalid Data Element Separator
027 Invalid Component Element Separator
028 Invalid delivery date in Deferred Delivery Request
029 Invalid delivery time in Deferred Delivery Request
030 Invalid delivery time Code in Deferred Delivery Request
031 Invalid grade of Service Code